

## Adding a Blu-ray Player to Your Harmony Remote

Posted At : 7 August 2010 19:24 | Posted By : Shaun McCran  
Related Categories: General Interest, Gadgets

I recently purchased a Blu-ray player and the picture on my TV has never looked better. I suspect that at some point, many of you will replace your DVD player with a Blu-ray player like me. So, I wanted to share with you the steps on how to add a Blu-ray player and to your Harmony remote using Logitech Harmony remote software.

The first step is to add your Blu-ray player to your Harmony remote account. To add your Blu-ray player:

Launch the Logitech Harmony Remote Software and login to your account

Click on the Devices tab

Click on Add Device

We currently don't have a category for Blu-ray players, so to add your Blu-ray player click on the -select device to add- dropdown and select DVD and then DVD again

Click on the -select manufacturer- dropdown and select the manufacturer

Enter the model name of your Blu-ray player. In this example I added a Sony BDP-S760

Device	Manufacturer	Model	Example
<input type="text" value="DVD"/>	<input type="text" value="Sony"/>	<input type="text" value="BDP-S760"/>	BDP-S350

Add another device

Click on the Next button

Confirm that you've entered in all of the information correctly, then click on the Next button to save your changes

Now that the Blu-ray player is added let's add an "Activity" to your Harmony remote. Since we currently don't have a "Watch Blu-ray" Activity selection, you will need to create a "Watch DVD" Activity. But don't worry, once you have finished creating the "Watch DVD" Activity, you can rename it to "Watch Blu-ray". Here are the steps to create the Activity:

From the Harmony Remote Software, click on the Activities tab

Click on the Add Activity button

Select No – manually add an Activity to my setup and click on the Next button

Select Watch DVD or Laserdisc and click the Next button

Again, we don't have a Blu-ray Activity so select Watch a DVD ( DVD player) click the Next button

Follow the instructions in the software to complete the setup of the Activity

Once completed, if you wish to rename the Activity to something more descriptive such as "Watch Blu-ray", refer to [this article](#) for steps on how to rename the Activity.

Watch DVD



Enter a new name for the Activity

Watch Blu-ray

The last step is to update your Harmony remote so that all the changes you have made will be transferred onto the remote.